

ASCII CHARACTER Set (0-127)

ThoughtAndMemory

.com.au

Microsoft Office Training



0000	N/S	0032	[space]	0064	@	0096	`
0001	N/S	0033	!	0065	A	0097	a
0002	N/S	0034	"	0066	B	0098	b
0003	N/S	0035	#	0067	C	0099	c
0004	N/S	0036	\$	0068	D	0100	d
0005	N/S	0037	%	0069	E	0101	e
0006	N/S	0038	&	0070	F	0102	f
0007	N/S	0039	'	0071	G	0103	g
0008	[backspace]	0040	(0072	H	0104	h
0009	[tab]	0041)	0073	I	0105	i
0010	[linefeed]	0042	*	0074	J	0106	j
0011	[linebreak]	0043	+	0075	K	0107	k
0012	N/S	0044	,	0076	L	0108	l
0013	[return]	0045	-	0077	M	0109	m
0014	N/S	0046	.	0078	N	0110	n
0015	N/S	0047	/	0079	O	0111	o
0016	N/S	0048	0	0080	P	0112	p
0017	N/S	0049	1	0081	Q	0113	q
0018	N/S	0050	2	0082	R	0114	r
0019	N/S	0051	3	0083	S	0115	s
0020	N/S	0052	4	0084	T	0116	t
0021	N/S	0053	5	0085	U	0117	u
0022	N/S	0054	6	0086	V	0118	v
0023	N/S	0055	7	0087	W	0119	w
0024	N/S	0056	8	0088	X	0120	x
0025	N/S	0057	9	0089	Y	0121	y
0026	N/S	0058	:	0090	Z	0122	z
0027	N/S	0059	;	0091	[0123	{
0028	N/S	0060	<	0092	\	0124	
0029	N/S	0061	=	0093]	0125	}
0030	N/S	0062	>	0094	^	0126	~
0031	N/S	0063	?	0095	_	0127	N/S

To Use the ASCII/ANSI keys... Hold down the ALT key, type the **4 digit** code using the **number keypad**.

Characters marked "N/S" are control characters which are not used in Windows

ANSI CHARACTER Set (128 - 255)

ThoughtAndMemory

.com.au

Microsoft Office Training



0128	€	0160	[space]	0192	À	0224	à	
0129	N/S	0161	¡	0193	Á	0225	á	
0130	‘	0162	¢	0194	Â	0226	â	
0131	f	0163	£	0195	Ã	0227	ã	
0132	„	0164	¤	0196	Ä	0228	ä	
0133	…	0165	¥	0197	Å	0229	å	
0134	†	0166	¦	0198	Æ	0230	æ	
0135	‡	0167	§	0199	Ç	0231	ç	
0136	^	0168	¨	0200	È	0232	è	
0137	%o	0169	©	0201	É	0233	é	
0138	Š	0170	ª	0202	Ê	0234	ê	
0139	<	0171	«	0203	Ë	0235	ë	
0140	Œ	0172	¬	0204	Ì	0236	ì	
0141	N/S	0173	-	0205	Í	0237	í	
0142	Ž	0174	®	0206	Î	0238	î	
0143	N/S	0175	¯	0207	Ï	0239	ï	
0144	N/S	0176	°	0208	Ð	0240	ð	
0145	‘	0177	±	0209	Ñ	0241	ñ	
0146	’	0178	²	0210	Ò	0242	ò	
0147	“	0179	³	0211	Ó	0243	ó	
0148	”	0180	´	0212	Ô	0244	ô	
0149	•	0181	µ	0213	Õ	0245	õ	
0150	—	0182	¶	0214	Ö	0246	ö	
0151	—	0183	·	0215	×	0247	÷	
0152	~	0184	,	0216	Ø	0248	ø	
0153	™	0185	¹	0217	Ù	0249	ù	
0154	š	0186	º	0218	Ú	0250	ú	
0155	>	0187	»	0219	Û	0251	û	✖
0156	œ	0188	¼	0220	Ü	0252	ü	✓
0157	N/S	0189	½	0221	Ý	0253	ý	✖
0158	ž	0190	¾	0222	Þ	0254	þ	✓
0159	ÿ	0191	¿	0223	ß	0255	ÿ	

To Use the ASCII/ANSI keys...Hold down the ALT key, type the **4 digit** code using the **number keypad**.

Note: Numbers 251-254 will give ticks and crosses if the font is changed to **Wingdings** before typing.